

---

# **LoFASM Documentation**

***Release 1***

**Louis Dartez**

**Dec 13, 2016**



# CONTENTS

<b>1</b>	<b>Indices and tables</b>	<b>3</b>
----------	---------------------------	----------



**class** lofasm.bbx.bbx.LofasmFile (lofasm\_file, verbose=False, mode='read', gz=None)

Class to represent .bbx-type data files for LoFASM.

Currently, the only data format supported is 'LoFASM-filterbank'.

**add\_data** (data)

add BBX data to memory to be written to file.

Write 1d or 2d data to memory to be written to disk. If invoked with a new file then the dimension fields in the metadata will be set.

**Parameters** **data** (*numpy.ndarray*) – Data array to be added to memory *data.ndim* must be either 1 or 2. The data type of the elements in the stored array will be inferred from *data*. Supported data types are *np.complex128* and *np.float64*.

**Raises**

- *AssertionError* – If file is not opened in write mode.
- *NotImplementedError* – If the dimensions of *data* are not supported.
- *ValueError* – If either the number of channels in *data* or the data type doesn't match the pre-existing data, if there is any.

**close** ()

close file object

**read\_data** (num\_time\_bin=None)

Parse data block in LoFASM filterbank file and load into memory as *self.data*.

The resulting data array in *self.data* is stored as a 2d array with *dim1* as the horizontal axis and *dim2* as the vertical axis.

If reading a typical LoFASM-filterbank file then the x-axis will represent the time bins and the y-axis will represent the frequency bins.

**Parameters** **num\_time\_bin** (*int*) – The number of time bins to read. If not provided, then attempt to read the entire file. If *num\_time\_bin* is larger than the number of time bins in the file then read the entire file. A value of 0 will result in nothing being read.

**Raises** *AssertionError* – If file is not open for reading

**set** (key, val)

Set header or metadata fields

Set or create header comment fields. If the field *key* exists then its value will be overwritten. If the field does not exist, then it will be created as a new comment field.

If *key* exists as part of the metadata field, then the value will be overwritten.

**Parameters**

- **key** (*str*) – Header field name as a string.
- **val** (*str, int, float*) – Value that header field will be set to

**write** ()

Write current data contents to disk.

If at the beginning of the file write the BBX header first, then the data.



## INDICES AND TABLES

- `genindex`